


## Installing C.A.T.S. Software on a PC Running Vista or Windows 7


All C.A.T.S. software can be installed on a PC running Microsoft Vista or Windows 7 but the installation process is a little different. Follow the following procedure to install a program on a PC running Vista or Windows 7:

1. Click on the Windows Start button and select 'Control Panel' from the option list. This will display the Windows Control Panel:




2. On the Control Panel screen click on 'Programs'.

3. On the next screen click on 'Use an older program with this version of Windows' under 'Programs and Features'




4. This will start the Program Compatibility Wizard.




5. Click on the 'Next' button to continue.
6. Next click on the 'I want to locate the program manually' option and then click on the next 'Next' button.




7. On the next screen click on the 'Browse' button.




8. Browse to the location to which you downloaded the setup program (for example tnr\_setup.exe for the OBDI Tuner program) or the CD ROM if you purchased one. Click on the setup program to highlight it and then click on the 'Open' button.




9. This screen confirms the file you have selected. Click on the 'Next' button to continue.




9. On the compatibility mode screen select 'Microsoft Windows XP (Service Pack 2)' and click on the Next button.



10. On the display settings screen leave all the options unchecked and click on the 'Next' button.




11. On the next screen check the 'Run this program as an administrator' box and click on the 'Next' button.




This will start the setup program. To complete the installation follow the on-screen instructions. Once the installation is complete the next compatibility wizard screen will be displayed.


12. Click on the 'Yes, set this program to always use these compatibility settings' option and click on the Next button.




13. On the Program Compatibility Data screen click on the 'No' option and then the 'Next' button.



14. The final compatibility wizard screen will then be displayed. Click the 'Finish' button to complete the installation.



15. Now that the program has been installed you need to set the program itself to run in compatibility mode using the Compatibility Wizard again. The Control Panel screen should now be visible so restart the Compatibility Wizard and follow the same process as before. When browsing for the application file, instead of selecting the setup program select the application file (wintnr.exe for the OBDI Tuner program). If you used the default installation folder this will be in the 'c:\program files\cats\'(program name)' folder.



16. Complete the rest of the Compatibility Wizard as described above to complete the installation.