## Installing the C.A.T.S. OBDI Tuner Program on a PC Running Windows 7, 8, 10 or 11

The OBDI Tuner program can be installed on a PC running Window 7, 8, 10 or 11 but the program needs to be installed to run in compatibility mode and as an administrator as follows:

- 1. Verify that you are logged on to your PC as an administrator.
- 2. Download the setup program for the latest version of the Tuner program from the 'Downloads' page on our web site at www.tunercat.com/software/tuner/tnr\_setup.exe and save it to your Desktop.
- 3. Double click on the setup program to install the Tuner program and follow the onscreen instruction to complete the installation. You may receive the follow message:



If you do get this message, just click on the 'Yes' button to continue the installation process.

4. After completing the installation set the Tuner program to run in compatibility mode. To do so, right click on the Tuner icon on your Desktop and select 'Properties' from the pop-up menu.

	Open
C.A. Tun	Open file location
	🖓 Run as administrator
	Troubleshoot compatibility
	Pin to Start
	Scan with Windows Defender
	Pin to taskbar
	Restore previous versions
	Send to >
	Cut
	Сору
	Create shortcut
	Delete
	Rename
	Properties -

5. Click the 'Compatibility' tab.

	C.A.T.S. Tune	r Proper	ies			×		
Tun	Security General		Details Shortcut	Pre	vious Versions Compatibility			
	С.А	C.A.T.S. Tuner						
	Target type: Target location: Target:	Application Tuner (C:\Progr	n ram Files (x86	)\CATS\T	uner\Wintnr.exe			
	Start in: Shortcut key:	Start in: "C:\Program Files (x86)\CATS\Tuner" Shortcut key: None						
	Run: Comment:	Normal v	vindow					
	Open File Lo	cation	Change k	con	Advanced			
	OK Cancel Apply							

6. On the Compatibility screen check the 'Run this program in compatibility mode for:' box, select Windows XP (Service Pack3), check the 'Run as administrator' box, click on the 'Apply' button and then click on the 'OK' button.

C.A.	👼 C.A.T.S. Tuner Properties							
Tun	Security	Details	Previous Versions					
	General	Shortcut	Compatibility					
	If this program isn't working correctly on this version of Windows, try running the compatibility troubleshooter. Run compatibility troubleshooter							
	How do I choose compatibility settings manually?							
	Compatibility mode							
	Run this program in compatibility mode for:							
	Windows XP (Service Pack 3) $\qquad \checkmark$							
		rmode						
	2.bit (256) color							
	Override high DPI scaling behavior.							
	Application							
	Disable fullscreen optimizations							
	Run this program as an administrator							
	Change settings for all users							
		OK	Cancel					
		UK	Cancer Apply	<u> </u>				